

Software Installation For Windows User

Install and register "ezcap HD Capture":

1. Install "ezcap HD capture"
ezcap HD Capture is a smart program to record video discs, game videos, homemade videos or anything from any video source under Windows OS working together with VG series device.


*Download ezcap HD Capture software from the official website :

<http://www.imvpin.com/>

Support > Files Download > ezcap_hd_capture software

Or, you can also choose with CD install software of "ezcap HD Capture" on your PC

*Double click the installation file and the setup wizard window will popup. Follow the installation wizard to complete the installation process. You do not have to restart your computer after the installation is completed.




Note: Prior to installing ezcap HD Capture, please make sure you are using Windows 7 or later versions and your PC is equipped with USB 2.0 or 3.0 port.

2. Register the ezcap HD Capture.

*Please register ezcap HD Capture first before using. Launch ezcap HD Capture. Click "Input registration code" button in the auto pop-up Register window. Fill in your proper Email address, real name and code. Then click "OK" to finish the registration.

* Obtain the registration code of ezcap HD Capture. Please check the code on the back of the device directly,



It is advised that you input your correct email address to receive the registration code at the same time. You may use the registration code, name and your email address to register ezcap HD Capture.



RECORD/CAPTURE VIDEOS TO PC.

Connect:


1. Connect the video player to the "IN" port on our VG device via an HDMI cable.
2. Connect the TV to the "OUTPUT" port on VG device via an HDMI cable.
3. Connect the USB3.0 cable between VG device and PC.

* For Windows

After all devices are connected properly, when you power on all devices, go to "Device manager", it will show "MYPIN HD Capture" or "ezcap U3 Capture" under "Cameras" and "Sound, video and game controllers":




Or if you are not connected properly, the software will remind you "Not found any capture device", please correctly connect our products and the screen will be displayed .




Record/Capture for Windows users


Please download or with CD install software of "ezcap HD Capture" on your PC. After all devices are connected properly, insert the video disc into the drive of the video player and run ezcap HD Capture.




(1) Click  to setup the "Video Resolution", "Frame rate", "Video Bitrate" as your need.




(2)Also,can setup the capture mode:



2. Click to start recording.




3. Click to stop recording. Tip: During recording, you can also click to pause at any-time.



When you want to resume, please click to continue recording.


Besides, you can Click to take screenshots, click to capture GIF animation by clicking.

4. After recording, click to view the recorded video. Then you can click to play back the video directly.




ezcap HD Capture also supports recording videos at the scheduled time.


Click to enter the 'Setup' window. Then click the "Schedule Recording" button.



Please enable schedule recording first, and set the Start time and duration for schedule recording. Then click "OK". Then videos will be recorded automatically at the scheduled time.



Video Broadcast Share: It can help you to playback captured videos on the smart phone or other PC.



Click the "Start Server" button to get the QR Code share the video.

